

# Package ‘adbcsqlite’

April 17, 2024

**Title** 'Arrow' Database Connectivity ('ADBC') 'SQLite' Driver

**Version** 0.11.0.1

**Description** Provides a developer-facing interface to the 'Arrow' Database Connectivity ('ADBC') 'SQLite' driver for the purposes of building high-level database interfaces for users. 'ADBC' <<https://arrow.apache.org/adbc/>> is an API standard for database access libraries that uses 'Arrow' for result sets and query parameters.

**License** Apache License (>= 2)

**Encoding** UTF-8

**RoxygenNote** 7.2.3

**SystemRequirements** SQLite3

**Suggests** nanoarrow, testthat (>= 3.0.0)

**Config/testthat/edition** 3

**Config/build/bootstrap** TRUE

**URL** <https://github.com/apache/arrow-adbc>,  
<https://arrow.apache.org/adbc/current/r/adbcsqlite/>

**BugReports** <https://github.com/apache/arrow-adbc/issues>

**Imports** adbcdrivermanager

**NeedsCompilation** yes

**Author** Dewey Dunnington [aut, cre] (<<https://orcid.org/0000-0002-9415-4582>>),  
Apache Arrow [aut, cph],  
Apache Software Foundation [cph]

**Maintainer** Dewey Dunnington <dewey@dunnington.ca>

**Repository** CRAN

**Date/Publication** 2024-04-17 19:40:19 UTC

## R topics documented:

adbcsqlite . . . . . 2

**Index** . . . . . 4

adbcsqlite

*ADBC SQLite3 Driver***Description**

ADBC SQLite3 Driver

**Usage**

```

adbcsqlite()

## S3 method for class 'adbcsqlite_driver_sqlite'
adbc_database_init(driver, ..., uri = ":memory:")

## S3 method for class 'adbcsqlite_database'
adbc_connection_init(database, ..., adbc.connection.autocommit = NULL)

## S3 method for class 'adbcsqlite_connection'
adbc_statement_init(
  connection,
  ...,
  adbc.ingest.target_table = NULL,
  adbc.ingest.mode = NULL,
  adbc.sqlite.query.batch_rows = NULL
)

```

**Arguments**

driver	An <a href="#">adbc_driver()</a> .
...	Driver-specific options. For the default method, these are named values that are converted to strings.
uri	A URI to a database path or ":memory:" for an in-memory database.
database	An <a href="#">adbc_database</a> .
adbc.connection.autocommit	Use FALSE to disable the default autocommit behaviour.
connection	An <a href="#">adbc_connection</a>
adbc.ingest.target_table	The name of the target table for a bulk insert.
adbc.ingest.mode	Whether to create (the default) or append.
adbc.sqlite.query.batch_rows	The number of rows per batch to return.

**Value**An [adbcdrivermanager::adbc\\_driver\(\)](#)

**Examples**

```
adbcsqlite()
```

# Index

`adb_connection`, [2](#)  
`adb_connection_init.adbcsqlite_database`  
    (`adbcsqlite`), [2](#)  
`adb_database`, [2](#)  
`adb_database_init.adbcsqlite_driver_sqlite`  
    (`adbcsqlite`), [2](#)  
`adb_driver()`, [2](#)  
`adb_statement_init.adbcsqlite_connection`  
    (`adbcsqlite`), [2](#)  
`adbdrivermanager::adb_driver()`, [2](#)  
`adbcsqlite`, [2](#)